

Race Manager - Feature #180

Cronolaps lapcounter support (TRANSLATE)

04/11/2023 05:00 PM - Jesús M. Broceño

Status:	Closed	Start date:	04/11/2023
Priority:	Normal	Due date:	
Assignee:	Jesús M. Broceño	% Done:	0%
Category:	Lap counter	Estimated time:	0:00 hour
Target version:	1.24.4		

Description

ZRound create a tcp service on a configurable serial port.

Detection messages are processed as lines terminated with \n (ascii 10) and they include four comma separated fields

Field	Description
00:1B:5F:00:C5:02	MAC
02E2017ABCD0000000004152	Transponder code
2023/03/26 15:24:51.824	Timestamp
1	Antenna

Example:

```
00:1B:5F:00:C5:02,02E2017ABCD0000000004152,2023/03/26 15:24:51.824,1
```

Translation

Race Manager

Spanish	English
Sistema impinj	Impinj System
Contraseña	Password
Configuración de mensaje en CronoNet	CronoNet configuration message
Activar servicio CronoNet	Activate CronoNet service
CronoNet	CronoNet
ZRound Desconectado	ZRound disconnected
Interfase con ZRound no disponible	ZRound interface not available
Sistema ZRound no puede iniciar la carrera	ZRound device can't start race
ZRound conectado	ZRound device connected
Puerto ZRound cerrado	ZRound port closed
ZRound no conectado	ZRound device disconnected
ZRound error:	ZRound device error:
ZRound conectando	ZRound device connecting
ZRound Activo	ZRound device active
ZRound - Error de conexión	ZRound device - Connection error
Interfase con CronoNet no disponible	Crononet interface not available
CronoNet Desconectado	Crononet disconnected
Sistema CronoNet no puede iniciar la carrera	CronoNet system can't start race
CronoNet conectado	CronoNet connected
Puerto CronoNet cerrado	CronoNet port closed

Spanish	English
CronoNet no conectado: %s	Crononet disconnected: %s
CronoNet error:	CronoNet error:
CronoNet conectando	Crononet connecting
CronoNet Activo	CronoNet active
CronoNet - Error de conexión	CronoNet - connection error
Sistema ZRound serial desactivado (%s) Para configurarlo utilice la ventana de opciones	ZRound serial device deactivated (%s). Use the ZRound Lapcounter settings windows to configure the device
Sistema CronoNet desactivado (%s) Para configurarlo utilice la ventana de opciones	CronoNet deactivated (%s). Use the CronoNet Lapcounter settings windows to configure the device
CronoNet interface OK	Crononet interface OK
ZRound serial interface OK	ZRound serial interface OK

History

#1 - 04/11/2023 06:48 PM - Jesús M. Broceño

- Description updated

- Status changed from New to In Progress

#2 - 04/22/2023 03:19 PM - Jesús M. Broceño

- Status changed from In Progress to Feedback

#3 - 04/25/2023 11:28 PM - Jesús M. Broceño

- Project changed from ZRound Suite to Race Manager

- Category changed from Lap counter to Lap counter

#4 - 06/04/2023 09:01 AM - Jesús M. Broceño

- Description updated

Added translation resources

#5 - 06/04/2023 09:16 AM - Jesús M. Broceño

- Description updated

#6 - 06/17/2023 05:49 PM - Jesús M. Broceño

- Status changed from Feedback to Closed

End user confirm the lapcounter works with ZRound flawlessly

#7 - 06/21/2023 08:22 PM - Jesús M. Broceño

- Subject changed from Crononet lapcounter support (TRANSLATE) to Cronolaps lapcounter support (TRANSLATE)